



# Guidelines for POTATOES

**Pre-plant Soil Application:** Apply *Soil Solution* @ 24 Oz/acre: This application should be made in the Fall and incorporated, or up to planting in the Spring. For No-till or over a growing crop, increase rate to 32 Oz/acre.

**Seed Potatoes for Bedding:** Apply *Seed Coat* @ 16 Oz per ton or acre of seed potatoes prior to or at Planting. *Seed Coat* may be mixed or diluted with a carrier such as fine gypsum to enhance coverage.

**Knifed into Seed Bed:** Apply *PercPlus* @ 16 Oz/acre in with liquid phosphate or nitrogen either in 2 X 2 or 6 X 6 application.

**Seedling Foliar:** After emergence (7 to 10 days). Foliar apply *PercPlus* @ 32 Oz/acre, *Zinc Plus* @ 16 Oz/acre, and *Boron Plus* @ 4 Oz/acre. Apply twice on 7 day intervals.  
**Option:** *MicroVite* @ 32 Oz/acre may be used as a substitute for *Zinc Plus* when other micronutrients are a concern.

**Initiation of Runners:** Apply foliar *PercPlus* @ 32 Oz/acre.

**Initial Bulking:** Foliar apply *CropKarb* @ 48 Oz/acre on weekly intervals for three to four applications.  
**Substitution** may be made with *Potassium Plus* @ 64 Oz, *PercPlus* @ 24 Oz and *Boron Plus* @ 6 Oz/acre.  
**NOTE:** If soil pH is low, add *Calcium Plus* @ 32 Oz to this combination.

**NOTE:** *CropKarb* may be replaced with a tank-mix of *Potassium Plus* @ 32 Oz, *PercPlus* @ 8 to 16 Oz, and *Boron Plus* @ 4 Oz.  
*Plant Power* may be substituted for *PercPlus* and vice-versa in any application and at the same rate.

**Mixing:** Always dilute *Potassium Plus* in water first, and follow with other ingredients in listed order to avoid excessive foaming.

These **DeltAg Guidelines** have been utilized to improve overall crop health and are not intended to be utilized as a replacement for basic and customary fertilizer applications. **“Other Crop Specific Guidelines are available upon request.”**