



# Guidelines for TOBACCO

July 2012

**Pre-plant Soil Application:** Apply *Soil Solution* @ 24 Oz/acre. This application should be made in the Fall and incorporated, or up to planting in the Spring. For No-till or over a growing crop, increase rate to 32 Oz/acre.

**Transplant Water:** Apply *PercPlus* @ 24 to 32 Oz/acre.

**Setting Foliar:** After initial shock of transplant (4-5 days): Apply *PercPlus* @ 16 Oz/acre.

**Seedling Foliar:** Foliar apply *PercPlus* @ 24 Oz/acre.

**Micronutrients:** Add *MicroVite* @ 32 Oz/acre in this application when any of these other nutrients are a concern: Magnesium, Sulfur, Copper, Manganese or Zinc.

**Five Weeks Before Topping Spray:** Apply foliar *CropKarb* @ 32 Oz/acre, *Boron Plus* @ 4 Oz and *Calcium Plus* @ 16 Oz/acre, on 7-10 day intervals for three applications BEFORE Topping. In stressful growing conditions, some growers have found benefit in the addition of *Magnesium Plus* at 16 Oz/acre and increasing the *Calcium Plus* to 32 Oz/acre in this mix. These applications may be applied with Fatty Alcohols.  
**NOTE:** Under Extreme Drought conditions, omit the additional *Boron Plus* listed above.

**Immediately After Topping:** Foliar *CropKarb* @ 32 Oz/acre.

**NOTE:** *CropKarb* may be replaced with a tank-mix of *Potassium Plus* @ 32 Oz, *PercPlus* @ 8 to 16 Oz, and *Boron Plus* @ 4 Oz. *Plant Power* may be substituted for *PercPlus* and vice-versa in any application and at the same rate.

**Mixing:** Always dilute *Potassium Plus* in water first, and follow with other ingredients in listed order to avoid excessive foaming.

These **DeltAg Guidelines** have been utilized to improve overall crop health and are not intended to be utilized as a replacement for basic and customary fertilizer applications. **“Other Crop Specific Guidelines are available upon request.”**